

Synology - ?? WireGuard ???

??????

□□□□

<https://synopackage.com/repository/spk/all> □□□

Wiregurad



Andreas Runfalk

WireGuard

已啟動

停用

Adds WireGuard support for your Synology NAS. ⚠ 本套件將以root权限运行！

其他資訊

開發者：

[Andreas Runfalk](#)

發行者：

[矿神SPK7](#)

已安裝版本：

1.0.20220627

????

□□□□□□

```
sudo sed -i 's/package/root/g' /var/packages/WireGuard/conf/privilege
```

```
□etc□□□□□wireguard□□□
```

```
mkdir /etc/wireguard/
```

```
□□Wireguard□□□
```

```
cd /etc/wireguard/
```

```
□□ conf □□□□
```

```
touch gw0.conf
```

```
□□□□□□□□
```

```
chmod 775 gw0.conf
```

????????

```
wg genkey | tee client1_privateKey | wg pubkey > client1_publicKey
```

??gw0.conf

[Interface]

PrivateKey = eEUEA8BW5RKWfUxXdAxZrotuKdZ5JZD9WQyVY= (client1_privateKey)

Address = 10.9.0.5/24 (server1ip)

MTU = 1400

PostUp = iptables -t nat -A POSTROUTING -o eth0 -s 10.9.0.0/24 -j MASQUERADE (wg up nat)

PostDown = iptables -t nat -D POSTROUTING -o eth0 -s 10.9.0.0/24 -j MASQUERADE (wg down nat)

[Peer]

PublicKey = RhlyTxxVzswNMlhBClPH7KB2jrrIOZUexE= (server1)

AllowedIPs = 10.9.0.0/24,192.168.0.0/24 (wg)

PersistentKeepalive = 25 (ping)

Endpoint = ip:port

WG

wg-quick up gw0

WG

wg-quick down gw0

WG

wg show gw0

#

sudo wg-autostart enable gw0

#

sudo wg-autostart disable gw0

Revision #4

Created 8 June 2025 04:35:02 by Jason

Updated 7 October 2025 03:40:55 by Jason